

Software Release Notes



Product: XRS2 and SRS2 Firmware

Version: 1.4.0

XRS2 and SRS2 –Version v1.4.0.1323- Released 19/06/2017

New features

Note: Some new features will create new Animal Data fields. If the feature is not present after updating the software you will need to delete some Animal Data fields, turn the XRS2 off and then back on.

- Offspring pairing
 - Enabled in the 'Tag Reading' menu
- Capability to add an Alert to an animal directly on the XRS2
 - By using the 'Alert' animal data field
- Print EID VID pairs to a Bluetooth printer
- The XRS2 can have the Bluetooth put into HID mode allowing EID tags to be sent directly to a PC
- Calculate Age from the DOB animal data field
- Display repeat and "+1" icon on favourite details screen
- Support non-EID recording
 - Search for the VID and then add the tag to the session
- Derive the VID number from the EID number

Bug fixes

- Fixed further non-standard animal tag issues
- Session field name/value could be overwritten
- Fixed duplicate check when a session is reopened
- Fixed alert settings not changing for some non English languages
- Minor bug fixes

XRS2 and SRS2 –Version v1.3.2.1124 - Released 12/01/2017

New features

- 15 animal data fields can now be recorded on the scan screen
- User can upload a new language
- Add date/time to the EID session record

Bug fixes

- Fixed enabling alerts bug that was present in some languages
- Fixed duplicate bug if a session is re-opened
- Fix to support non animal tags
- Minor bug fixes

XRS2 and SRS2 - Version 1.3.0.1040 – Web released 07/11/2016 (version 1.3.0.1083 Production released)

New features

- Animal look up using an ID field
- VID auto increment (+1)
- Hide VID
- Change EID wizard
- EID/VID change is stored and saved in animal notes for the session
- Delete any animal from the session list
- Delete paired Bluetooth devices
- Warning screen added before changing a VID
- Added screen to view session description
- Default breed order updated to match 5000 series

Bug fixes

- Minor Bugs fixed

XRS2 and SRS2 - Version 1.02.0013 - Released 07/10/2016

Bug fixes

- XRS2 and SRS2 sometimes crashed unexpectedly.

XRS2 and SRS2 - Version 1.02.0001 - Released 10/08/2016

New features

- Performance enhancements.
- A language/country selection wizard has now been added.
- Favourites - names and descriptions have now been translated.
- Session names have now been translated.
- *Bluetooth*[®] wireless communications – an error code will now be sent if the device is communicating with Data Link via the serial port.
- Improvements to wording/translations.

Bug fixes

- Screen was not refreshing properly when a session had been deleted.
- Some life data values (values from a drop-down list) were not being converted correctly.
- Communication commands used by third-party software - Wrong response for {FH} if user deletes an animal data in the user interface.
- Communication commands used by third-party software - Sometimes {SOCU} and {ADDA} could make the device crash.

XRS2 and SRS2 - Version 1.01.0000 - Released 26/07/2016

New features

- Performance enhancements.
- Validate and correct date format on scan screen.
- The default names used for animal data fields have now been translated.
- Some minor wording changes.

Bug fixes

- Animal data fields – it is now possible to set an animal data field as blank.
- Animal data fields – A prefix can now be added to an ID field (was not working correctly in initial release).

XRS2 and SRS2 - Version 1.00.0004 - Released 20/07/2016

New features

- Initial production release